


## Lab - Configuring VLANs and Trunking (Solution)

### Topology



### Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
S1	VLAN 1	192.168.1.11	255.255.255.0	N/A
S2	VLAN 1	192.168.1.12	255.255.255.0	N/A
PC-A	NIC	192.168.10.3	255.255.255.0	192.168.10.1
PC-B	NIC	192.168.10.4	255.255.255.0	192.168.10.1
PC-C	NIC	192.168.20.3	255.255.255.0	192.168.20.1

### Objectives

**Part 1: Build the Network and Configure Basic Device Settings**

**Part 2: Create VLANs and Assign Switch Ports**

**Part 3: Maintain VLAN Port Assignments and the VLAN Database**

**Part 4: Configure an 802.1Q Trunk between the Switches**

**Part 5: Delete the VLAN Database**

### Background / Scenario

Modern switches use virtual local-area networks (VLANs) to improve network performance by separating large Layer 2 broadcast domains into smaller ones. VLANs can also be used as a security measure by controlling which hosts can communicate. In general, VLANs make it easier to design a network to support the goals of an organization.

VLAN trunks are used to span VLANs across multiple devices. Trunks allow the traffic from multiple VLANs to travel over a single link, while keeping the VLAN identification and segmentation intact.

In this lab, you will create VLANs on both switches in the topology, assign VLANs to switch access ports, verify that VLANs are working as expected, and then create a VLAN trunk between the two switches to allow hosts in the same VLAN to communicate through the trunk, regardless of which switch the host is actually attached to.

**Note:** The switches used are Cisco Catalyst 2960s with Cisco IOS Release 15.0(2) (lanbasek9 image). Other switches and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and output produced might vary from what is shown in the labs.

**Note:** Ensure that the switches have been erased and have no startup configurations. If you are unsure contact your instructor.

### Required Resources

- 2 Switches (Cisco 2960 with Cisco IOS Release 15.0(2) lanbasek9 image or comparable)
- 3 PCs (Windows 7, Vista, or XP with terminal emulation program, such as Tera Term)
- Console cables to configure the Cisco IOS devices via the console ports
- Ethernet cables as shown in the topology

## Part 1: Build the Network and Configure Basic Device Settings

In Part 1, you will set up the network topology and configure basic settings on the PC hosts and switches.

### Step 1: Cable the network as shown in the topology.

Attach the devices as shown in the topology diagram, and cable as necessary.

### Step 2: Initialize and reload the switches as necessary.

### Step 3: Configure basic settings for each switch.

- a. Console into the switch and enter global configuration mode.
- b. Copy the following basic configuration and paste it to the running-configuration on the switch.

```
no ip domain-lookup
service password-encryption
enable secret class
banner motd #
Unauthorized access is strictly prohibited. #
line con 0
password cisco
login
logging synchronous
line vty 0 15
password cisco
logging synchronous
login
exit
```

- c. Configure the host name as shown in the topology.

- d. Configure the IP address listed in the Addressing Table for VLAN 1 on the switch.
- e. Administratively deactivate all unused ports on the switch.
- f. Copy the running configuration to the startup configuration.

### Step 4: Configure PC hosts.

Refer to the Addressing Table for PC host address information.

### Step 5: Test connectivity.

Verify that the PC hosts can ping one another.

**Note:** It may be necessary to disable the PCs firewall to ping between PCs.

Can PC-A ping PC-B? \_\_\_\_\_ **Yes**

Can PC-A ping PC-C? \_\_\_\_\_ **No**

Can PC-A ping S1? \_\_\_\_\_ **No**

Can PC-B ping PC-C? \_\_\_\_\_ **No**

Can PC-B ping S2? \_\_\_\_\_ **No**

Can PC-C ping S2? \_\_\_\_\_ **No**

Can S1 ping S2? \_\_\_\_\_ **Yes**

If you answered no to any of the above questions, why were the pings unsuccessful?

---

Pings were unsuccessful when trying to ping a device on a different subnet. For those pings to be successful, a default gateway must exist to route traffic from one subnet to another.

## Part 2: Create VLANs and Assign Switch Ports

In Part 2, you will create student, faculty, and management VLANs on both switches. You will then assign the VLANs to the appropriate interface. The **show vlan** command is used to verify your configuration settings.

### Step 1: Create VLANs on the switches.

- a. Create the VLANs on S1.

```
S1(config)# vlan 10
S1(config-vlan)# name Student
S1(config-vlan)# vlan 20
S1(config-vlan)# name Faculty
S1(config-vlan)# vlan 99
S1(config-vlan)# name Management
S1(config-vlan)# end
```

- b. Create the same VLANs on S2.

- c. Issue the **show vlan** command to view the list of VLANs on S1.

```
S1# show vlan
```

VLAN Name	Status	Ports
-----------	--------	-------

## Lab - Configuring VLANs and Trunking

```
-----
1      default                                active    Fa0/1, Fa0/2, Fa0/3, Fa0/4
                                                Fa0/5, Fa0/6, Fa0/7, Fa0/8
                                                Fa0/9, Fa0/10, Fa0/11, Fa0/12
                                                Fa0/13, Fa0/14, Fa0/15, Fa0/16
                                                Fa0/17, Fa0/18, Fa0/19, Fa0/20
                                                Fa0/21, Fa0/22, Fa0/23, Fa0/24
                                                Gi0/1, Gi0/2
```

```
10     Student                                active
```

```
20     Faculty                                active
```

```
99     Management                             active
```

```
1002   fddi-default                           act/unsup
```

```
1003   token-ring-default                     act/unsup
```

```
1004   fddinet-default                        act/unsup
```

```
1005   trnet-default                          act/unsup
```

VLAN	Type	SAID	MTU	Parent	RingNo	BridgeNo	Stp	BrdgMode	Trans1	Trans2
1	enet	100001	1500	-	-	-	-	-	0	0
10	enet	100010	1500	-	-	-	-	-	0	0
20	enet	100020	1500	-	-	-	-	-	0	0
99	enet	100099	1500	-	-	-	-	-	0	0

VLAN	Type	SAID	MTU	Parent	RingNo	BridgeNo	Stp	BrdgMode	Trans1	Trans2
1002	fddi	101002	1500	-	-	-	-	-	0	0
1003	tr	101003	1500	-	-	-	-	-	0	0
1004	fdnet	101004	1500	-	-	-	ieee	-	0	0
1005	trnet	101005	1500	-	-	-	ibm	-	0	0

Remote SPAN VLANs

```
-----
Primary Secondary Type                      Ports
-----
```

What is the default VLAN? \_\_\_\_\_ **VLAN 1**

What ports are assigned to the default VLAN?

---

**All switch ports are assigned to VLAN 1 by default.**

### Step 2: Assign VLANs to the correct switch interfaces.

- a. Assign VLANs to the interfaces on S1.

- 1) Assign PC-A to the Student VLAN.

```
S1(config)# interface f0/6
```

```
S1(config-if)# switchport mode access
```

```
S1(config-if)# switchport access vlan 10
```

- 2) Move the switch IP address VLAN 99.

```
S1(config)# interface vlan 1
S1(config-if)# no ip address
S1(config-if)# interface vlan 99
S1(config-if)# ip address 192.168.1.11 255.255.255.0
S1(config-if)# end
```

- b. Issue the **show vlan brief** command and verify that the VLANs are assigned to the correct interfaces.

```
S1# show vlan brief
```

VLAN	Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/7, Fa0/8, Fa0/9 Fa0/10, Fa0/11, Fa0/12, Fa0/13 Fa0/14, Fa0/15, Fa0/16, Fa0/17 Fa0/18, Fa0/19, Fa0/20, Fa0/21 Fa0/22, Fa0/23, Fa0/24, Gi0/1 Gi0/2
10	Student	active	Fa0/6
20	Faculty	active	
99	Management	active	
1002	fddi-default	act/unsup	
1003	token-ring-default	act/unsup	
1004	fddinet-default	act/unsup	
1005	trnet-default	act/unsup	

- c. Issue the **show ip interface brief** command.

```
S1# show ip interface brief
```

Interface	IP-Address	OK?	Method	Status	Protocol
Vlan1	unassigned	YES	unset	up	up
Vlan99	192.168.1.11	YES	manual	up	down
FastEthernet0/1	unassigned	YES	unset	up	up
FastEthernet0/2	unassigned	YES	unset	administratively down	down
FastEthernet0/3	unassigned	YES	unset	administratively down	down
FastEthernet0/4	unassigned	YES	unset	administratively down	down
FastEthernet0/5	unassigned	YES	unset	administratively down	down
FastEthernet0/6	unassigned	YES	unset	up	up
FastEthernet0/7	unassigned	YES	unset	administratively down	down

<output omitted>

What is the status of VLAN 99? Why?

---

The status of VLAN 99 is up/down, because it has not been assigned to an active port yet.

- d. Use the Topology to assign VLANs to the appropriate ports on S2.  
e. Remove the IP address for VLAN 1 on S2.

- f. Configure an IP address for VLAN 99 on S2 according to the Addressing Table.
- g. Use the **show vlan brief** command to verify that the VLANs are assigned to the correct interfaces.

S2# **show vlan brief**

VLAN	Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/6, Fa0/7, Fa0/8 Fa0/9, Fa0/10, Fa0/12, Fa0/13 Fa0/14, Fa0/15, Fa0/16, Fa0/17 Fa0/19, Fa0/20, Fa0/21, Fa0/22 Fa0/23, Fa0/24, Gi0/1, Gi0/2
10	Student	active	Fa0/11
20	Faculty	active	Fa0/18
99	Management	active	
1002	fddi-default	act/unsup	
1003	token-ring-default	act/unsup	
1004	fddinet-default	act/unsup	
1005	trnet-default	act/unsup	

Is PC-A able to ping PC-B? Why?

No. Interface F0/1 is not assigned to VLAN 10, so VLAN 10 traffic will not be sent over it.

Is S1 able to ping S2? Why?

No. The IP addresses for the switches now reside in VLAN 99. VLAN 99 traffic will not be sent over interface F0/1.

## Part 3: Maintain VLAN Port Assignments and the VLAN Database

In Part 3, you will change VLAN assignments to ports and remove VLANs from the VLAN database.

### Step 1: Assign a VLAN to multiple interfaces.

- a. On S1, assign interfaces F0/11 – 24 to VLAN 10.  
S1(config)# **interface range f0/11-24**  
S1(config-if-range)# **switchport mode access**  
S1(config-if-range)# **switchport access vlan 10**  
S1(config-if-range)# **end**
- b. Issue the **show vlan brief** command to verify VLAN assignments.

S1# **show vlan brief**

VLAN	Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/7, Fa0/8, Fa0/9 Fa0/10, Gi0/1, Gi0/2

```
10 Student active Fa0/6, Fa0/11, Fa0/12, Fa0/13
Fa0/14, Fa0/15, Fa0/16, Fa0/17
Fa0/18, Fa0/19, Fa0/20, Fa0/21
Fa0/22, Fa0/23, Fa0/24
20 Faculty active
99 Management active
1002 fddi-default act/unsup
1003 token-ring-default act/unsup
1004 fddinet-default act/unsup
1005 trnet-default act/unsup
```

- c. Reassign F0/11 and F0/21 to VLAN 20.

```
S1(config)# interface range f0/11, f0/21
S1(config-if-range)# switchport access vlan 20
S1(config-if-range)# end
```

- d. Verify that VLAN assignments are correct.

```
S1# show vlan brief
```

VLAN	Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/7, Fa0/8, Fa0/9 Fa0/10, Gi0/1, Gi0/2
10	Student	active	Fa0/6, Fa0/12, Fa0/13, Fa0/14 Fa0/15, Fa0/16, Fa0/17, Fa0/18 Fa0/19, Fa0/20, Fa0/22, Fa0/23 Fa0/24
20	Faculty	active	Fa0/11, Fa0/21
99	Management	active	
1002	fddi-default	act/unsup	
1003	token-ring-default	act/unsup	
1004	fddinet-default	act/unsup	
1005	trnet-default	act/unsup	

### Step 2: Remove a VLAN assignment from an interface.

- a. Use the **no switchport access vlan** command to remove the VLAN 10 assignment to F0/24.

```
S1(config)# interface f0/24
S1(config-if)# no switchport access vlan
S1(config-if)# end
```

- b. Verify that the VLAN change was made.

Which VLAN is F0/24 now associated with?

```
VLAN 1, the default VLAN.
```

```
S1# show vlan brief
```

VLAN	Name	Status	Ports
------	------	--------	-------

1	default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/7, Fa0/8, Fa0/9 Fa0/10, Fa0/24, Gi0/1, Gi0/2
10	Student	active	Fa0/6, Fa0/12, Fa0/13, Fa0/14 Fa0/15, Fa0/16, Fa0/17, Fa0/18 Fa0/19, Fa0/20, Fa0/22, Fa0/23
20	Faculty	active	Fa0/11, Fa0/21
99	Management	active	
1002	fddi-default	act/unsup	
1003	token-ring-default	act/unsup	
1004	fddinet-default	act/unsup	
1005	trnet-default	act/unsup	

### Step 3: Remove a VLAN ID from the VLAN database.

- a. Add VLAN 30 to interface F0/24 without issuing the VLAN command.

```
S1(config)# interface f0/24
S1(config-if)# switchport access vlan 30
% Access VLAN does not exist. Creating vlan 30
```

**Note:** Current switch technology no longer requires that the **vlan** command be issued to add a VLAN to the database. By assigning an unknown VLAN to a port, the VLAN adds to the VLAN database.

- b. Verify that the new VLAN is displayed in the VLAN table.

```
S1# show vlan brief
```

VLAN	Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/6, Fa0/7, Fa0/8 Fa0/9, Fa0/10, Gi0/1, Gi0/2
10	Student	active	Fa0/12, Fa0/13, Fa0/14, Fa0/15 Fa0/16, Fa0/17, Fa0/18, Fa0/19 Fa0/20, Fa0/22, Fa0/23
20	Faculty	active	Fa0/11, Fa0/21
30	VLAN0030	active	Fa0/24
99	Management	active	
1002	fddi-default	act/unsup	
1003	token-ring-default	act/unsup	
1004	fddinet-default	act/unsup	
1005	trnet-default	act/unsup	

What is the default name of VLAN 30?

VLAN0030

- c. Use the **no vlan 30** command to remove VLAN 30 from the VLAN database.

```
S1(config)# no vlan 30
S1(config)# end
```

- d. Issue the **show vlan brief** command. F0/24 was assigned to VLAN 30.



After deleting VLAN 30, what VLAN is port F0/24 assigned to? What happens to the traffic destined to the host attached to F0/24?

---

Port F0/24 is not assigned to any VLAN. This port will not transfer any traffic.

S1# **show vlan brief**

VLAN	Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/6, Fa0/7, Fa0/8 Fa0/9, Fa0/10, Gi0/1, Gi0/2
10	Student	active	Fa0/12, Fa0/13, Fa0/14, Fa0/15 Fa0/16, Fa0/17, Fa0/18, Fa0/19 Fa0/20, Fa0/22, Fa0/23
20	Faculty	active	Fa0/11, Fa0/21
99	Management	active	
1002	fddi-default	act/unsup	
1003	token-ring-default	act/unsup	
1004	fddinet-default	act/unsup	
1005	trnet-default	act/unsup	

- e. Issue the **no switchport access vlan** command on interface F0/24.

```
S1(config)# interface f0/24
S1(config-if)# no switchport access vlan
S1(config-if)# end
```

- f. Issue the **show vlan brief** command to determine the VLAN assignment for F0/24. To which VLAN is F0/24 assigned?

---

### VLAN 1

S1# **show vlan brief**

VLAN	Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/7, Fa0/8, Fa0/9 Fa0/10, Fa0/24, Gi0/1, Gi0/2
10	Student	active	Fa0/6, Fa0/12, Fa0/13, Fa0/14 Fa0/15, Fa0/16, Fa0/17, Fa0/18 Fa0/19, Fa0/20, Fa0/22, Fa0/23
20	Faculty	active	Fa0/11, Fa0/21
99	Management	active	
1002	fddi-default	act/unsup	
1003	token-ring-default	act/unsup	
1004	fddinet-default	act/unsup	
1005	trnet-default	act/unsup	

**Note:** Before removing a VLAN from the database, it is recommended that you reassign all the ports assigned to that VLAN.

Why should you reassign a port to another VLAN before removing the VLAN from the VLAN database?

The interfaces assigned to a VLAN that is removed from the VLAN database are unavailable for use until they are reassigned to another VLAN. This can be a tricky thing to troubleshoot as trunked interfaces do not show up in the port list as well (Part 4 contains more information about trunked interfaces).

### Part 4: Configure an 802.1Q Trunk Between the Switches

In Part 4, you will configure interface F0/1 to use the Dynamic Trunking Protocol (DTP) to allow it to negotiate the trunk mode. After this has been accomplished and verified, you will disable DTP on interface F0/1 and manually configure it as a trunk.

#### Step 1: Use DTP to initiate trunking on F0/1.

The default DTP mode of a 2960 switch port is dynamic auto. This allows the interface to convert the link to a trunk if the neighboring interface is set to trunk or dynamic desirable mode.

- a. Set F0/1 on S1 to negotiate trunk mode.

```
S1(config)# interface f0/1
S1(config-if)# switchport mode dynamic desirable
*Mar 1 05:07:28.746: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan1, changed
state to down
*Mar 1 05:07:29.744: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to down
S1(config-if)#
*Mar 1 05:07:32.772: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to up
S1(config-if)#
*Mar 1 05:08:01.789: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan99, changed
state to up
*Mar 1 05:08:01.797: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan1, changed
state to up
```

You should also receive link status messages on S2.

```
S2#
*Mar 1 05:07:29.794: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to down
S2#
*Mar 1 05:07:32.823: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to up
S2#
*Mar 1 05:08:01.839: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan99, changed
state to up
*Mar 1 05:08:01.850: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan1, changed
state to up
```

- b. Issue the **show vlan brief** command on S1 and S2. Interface F0/1 is no longer assigned to VLAN 1. Trunked interfaces are not listed in the VLAN table.

```
S1# show vlan brief
```

## Lab - Configuring VLANs and Trunking

VLAN	Name	Status	Ports
1	default	active	Fa0/2, Fa0/3, Fa0/4, Fa0/5 Fa0/7, Fa0/8, Fa0/9, Fa0/10 Fa0/24, Gi0/1, Gi0/2
10	Student	active	Fa0/6, Fa0/12, Fa0/13, Fa0/14 Fa0/15, Fa0/16, Fa0/17, Fa0/18 Fa0/19, Fa0/20, Fa0/22, Fa0/23
20	Faculty	active	Fa0/11, Fa0/21
99	Management	active	
1002	fddi-default	act/unsup	
1003	token-ring-default	act/unsup	
1004	fddinet-default	act/unsup	
1005	trnet-default	act/unsup	

- c. Issue the **show interfaces trunk** command to view trunked interfaces. Notice that the mode on S1 is set to desirable, and the mode on S2 is set to auto.

S1# **show interfaces trunk**

Port	Mode	Encapsulation	Status	Native vlan
Fa0/1	desirable	802.1q	trunking	1

Port	Vlans allowed on trunk
Fa0/1	1-4094

Port	Vlans allowed and active in management domain
Fa0/1	1,10,20,99

Port	Vlans in spanning tree forwarding state and not pruned
Fa0/1	1,10,20,99

S2# **show interfaces trunk**

Port	Mode	Encapsulation	Status	Native vlan
Fa0/1	auto	802.1q	trunking	1

Port	Vlans allowed on trunk
Fa0/1	1-4094

Port	Vlans allowed and active in management domain
Fa0/1	1,10,20,99

Port	Vlans in spanning tree forwarding state and not pruned
Fa0/1	1,10,20,99

**Note:** By default, all VLANs are allowed on a trunk. The **switchport trunk** command allows you to control what VLANs have access to the trunk. For this lab, keep the default settings which allows all VLANs to traverse F0/1.

- d. Verify that VLAN traffic is traveling over trunk interface F0/1.

Can S1 ping S2? \_\_\_\_\_ Yes

Can PC-A ping PC-B? \_\_\_\_\_ Yes  
Can PC-A ping PC-C? \_\_\_\_\_ No  
Can PC-B ping PC-C? \_\_\_\_\_ No  
Can PC-A ping S1? \_\_\_\_\_ No  
Can PC-B ping S2? \_\_\_\_\_ No  
Can PC-C ping S2? \_\_\_\_\_ No

If you answered no to any of the above questions, explain below.

---

PC-C cannot ping PC-A or PC-B because PC-C is in a different VLAN. The switches are in different VLANs than the PCs; therefore, the pings were unsuccessful.

### Step 2: Manually configure trunk interface F0/1.

The **switchport mode trunk** command is used to manually configure a port as a trunk. This command should be issued on both ends of the link.

- a. Change the switchport mode on interface F0/1 to force trunking. Make sure to do this on both switches.

```
S1(config)# interface f0/1
S1(config-if)# switchport mode trunk
```

```
S2(config)# interface f0/1
S2(config-if)# switchport mode trunk
```

- b. Issue the **show interfaces trunk** command to view the trunk mode. Notice that the mode changed from **desirable** to **on**.

```
S2# show interfaces trunk
```

Port	Mode	Encapsulation	Status	Native vlan
Fa0/1	on	802.1q	trunking	99

Port	Vlans allowed on trunk
Fa0/1	1-4094

Port	Vlans allowed and active in management domain
Fa0/1	1,10,20,99

Port	Vlans in spanning tree forwarding state and not pruned
Fa0/1	1,10,20,99

Why might you want to manually configure an interface to trunk mode instead of using DTP?

---

Not all equipment uses DTP. Using the **switchport mode trunk** command ensures that the port will become a trunk no matter what type of equipment is connected to the other end of the link.

### Part 5: Delete the VLAN Database

In Part 5, you will delete the VLAN Database from the switch. It is necessary to do this when initializing a switch back to its default settings.

#### Step 1: Determine if the VLAN database exists.

Issue the **show flash** command to determine if a **vlan.dat** file exists in flash.

```
S1# show flash
```

```
Directory of flash:/
```

2	-rwx	1285	Mar 1 1993 00:01:24 +00:00	config.text
3	-rwx	43032	Mar 1 1993 00:01:24 +00:00	multiple-fs
4	-rwx	5	Mar 1 1993 00:01:24 +00:00	private-config.text
5	-rwx	11607161	Mar 1 1993 02:37:06 +00:00	c2960-lanbasek9-mz.150-2.SE.bin
6	-rwx	736	Mar 1 1993 00:19:41 +00:00	vlan.dat

```
32514048 bytes total (20858880 bytes free)
```

**Note:** If there is a **vlan.dat** file located in flash, then the VLAN database does not contain its default settings.

#### Step 2: Delete the VLAN database.

- Issue the **delete vlan.dat** command to delete the **vlan.dat** file from flash and reset the VLAN database back to its default settings. You will be prompted twice to confirm that you want to delete the **vlan.dat** file. Press Enter both times.

```
S1# delete vlan.dat
```

```
Delete filename [vlan.dat]?
```

```
Delete flash:/vlan.dat? [confirm]
```

```
S1#
```

- Issue the **show flash** command to verify that the **vlan.dat** file has been deleted.

```
S1# show flash
```

```
Directory of flash:/
```

2	-rwx	1285	Mar 1 1993 00:01:24 +00:00	config.text
3	-rwx	43032	Mar 1 1993 00:01:24 +00:00	multiple-fs
4	-rwx	5	Mar 1 1993 00:01:24 +00:00	private-config.text
5	-rwx	11607161	Mar 1 1993 02:37:06 +00:00	c2960-lanbasek9-mz.150-2.SE.bin

```
32514048 bytes total (20859904 bytes free)
```

To initialize a switch back to its default settings, what other commands are needed?

---

To get a switch back to its default settings, the **erase startup-config** and **reload** commands need to be issued after the **delete vlan.dat** command.

### Reflection

1. What is needed to allow hosts on VLAN 10 to communicate to hosts on VLAN 20?

Answers will vary, but Layer 3 routing is needed to route traffic between VLANs.

2. What are some primary benefits that an organization can receive through effective use of VLANs?

Answers will vary, but VLAN benefits include: better security, cost savings (efficient use of bandwidth and uplinks), higher performance (smaller broadcast domains), broadcast storm mitigation, improved IT staff efficiency, simpler project and application management.

### Device Configs - Final

#### Switch S1

Building configuration...

Current configuration : 2571 bytes

```
!  
version 15.0  
no service pad  
service timestamps debug datetime msec  
service timestamps log datetime msec  
no service password-encryption  
!  
hostname S1  
!  
boot-start-marker  
boot-end-marker  
!  
enable secret 4 06YFDUHH61wAE/kLkDq9BGho1QM5EnRtoyr8cHAUg.2  
!  
no aaa new-model  
system mtu routing 1500  
!  
no ip domain-lookup  
!  
spanning-tree mode pvst  
spanning-tree extend system-id  
!  
vlan internal allocation policy ascending  
!  
interface FastEthernet0/1  
  switchport mode trunk
```

```
!  
interface FastEthernet0/2  
shutdown  
!  
interface FastEthernet0/3  
shutdown  
!  
interface FastEthernet0/4  
shutdown  
!  
interface FastEthernet0/5  
shutdown  
!  
interface FastEthernet0/6  
switchport access vlan 10  
switchport mode access  
!  
interface FastEthernet0/7  
shutdown  
!  
interface FastEthernet0/8  
shutdown  
!  
interface FastEthernet0/9  
shutdown  
!  
interface FastEthernet0/10  
shutdown  
!  
interface FastEthernet0/11  
switchport access vlan 20  
switchport mode access  
shutdown  
!  
interface FastEthernet0/12  
switchport access vlan 10  
switchport mode access  
shutdown  
!  
interface FastEthernet0/13  
switchport access vlan 10  
switchport mode access  
shutdown  
!  
interface FastEthernet0/14  
switchport access vlan 10  
switchport mode access  
shutdown  
!
```

## Lab - Configuring VLANs and Trunking

---

```
interface FastEthernet0/15
  switchport access vlan 10
  switchport mode access
  shutdown
!
interface FastEthernet0/16
  switchport access vlan 10
  switchport mode access
  shutdown
!
interface FastEthernet0/17
  switchport access vlan 10
  switchport mode access
  shutdown
!
interface FastEthernet0/18
  switchport access vlan 10
  switchport mode access
  shutdown
!
interface FastEthernet0/19
  switchport access vlan 10
  switchport mode access
  shutdown
!
interface FastEthernet0/20
  switchport access vlan 10
  switchport mode access
  shutdown
!
interface FastEthernet0/21
  switchport access vlan 20
  switchport mode access
  shutdown
!
interface FastEthernet0/22
  switchport access vlan 10
  switchport mode access
  shutdown
!
interface FastEthernet0/23
  switchport access vlan 10
  switchport mode access
  shutdown
!
interface FastEthernet0/24
  switchport mode access
  shutdown
!
```



```
interface GigabitEthernet0/1
 shutdown
!
interface GigabitEthernet0/2
 shutdown
!
interface Vlan1
 no ip address
!
interface Vlan99
 ip address 192.168.1.11 255.255.255.0
!
ip http server
ip http secure-server
!
!
banner motd ^C
  Unauthorized Access is Prohibited!
^C
!
line con 0
 password cisco
 logging synchronous
 login
line vty 0 4
 password cisco
 login
line vty 5 15
 password cisco
 login
!
end
```

### Switch S2

Building configuration...

```
Current configuration : 1875 bytes
!
version 15.0
no service pad
service timestamps debug datetime msec
service timestamps log datetime msec
no service password-encryption
!
hostname S2
!
boot-start-marker
boot-end-marker
!
```

```
enable secret 4 06YFDUHH61wAE/kLkDq9BGho1QM5EnRtoyr8cHAUg.2
!
no aaa new-model
system mtu routing 1500
!
no ip domain-lookup
!
spanning-tree mode pvst
spanning-tree extend system-id
!
vlan internal allocation policy ascending
!
interface FastEthernet0/1
  switchport mode trunk
!
interface FastEthernet0/2
  shutdown
!
interface FastEthernet0/3
  shutdown
!
interface FastEthernet0/4
  shutdown
!
interface FastEthernet0/5
  shutdown
!
interface FastEthernet0/6
  shutdown
!
interface FastEthernet0/7
  shutdown
!
interface FastEthernet0/8
  shutdown
!
interface FastEthernet0/9
  shutdown
!
interface FastEthernet0/10
  shutdown
!
interface FastEthernet0/11
  switchport access vlan 10
  switchport mode access
!
interface FastEthernet0/12
  shutdown
!
```

```
interface FastEthernet0/13
shutdown
!
interface FastEthernet0/14
shutdown
!
interface FastEthernet0/15
shutdown
!
interface FastEthernet0/16
shutdown
!
interface FastEthernet0/17
shutdown
!
interface FastEthernet0/18
switchport access vlan 20
switchport mode access
!
interface FastEthernet0/19
shutdown
!
interface FastEthernet0/20
shutdown
!
interface FastEthernet0/21
shutdown
!
interface FastEthernet0/22
shutdown
!
interface FastEthernet0/23
shutdown
!
interface FastEthernet0/24
shutdown
!
interface GigabitEthernet0/1
shutdown
!
Interface GigabitEthernet0/2
shutdown
!
interface Vlan1
no ip address
!
interface Vlan99
ip address 192.168.1.12 255.255.255.0
!
```

## Lab - Configuring VLANs and Trunking

---

```
ip http server
ip http secure-server
!
!
banner motd ^C
  Unauthorized Access is Prohibited!
^C
!
line con 0
  password cisco
  logging synchronous
  login
line vty 0 4
  password cisco
  login
line vty 5 15
  password cisco
  login
!
end
```