


Lab – Configuring Per-Interface Inter-VLAN Routing (Solution)

Topology



Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	G0/0	192.168.20.1	255.255.255.0	N/A
	G0/1	192.168.10.1	255.255.255.0	N/A
S1	VLAN 10	192.168.10.11	255.255.255.0	192.168.10.1
S2	VLAN 10	192.168.10.12	255.255.255.0	192.168.10.1
PC-A	NIC	192.168.10.3	255.255.255.0	192.168.10.1
PC-B	NIC	192.168.20.3	255.255.255.0	192.168.20.1

Objectives

Part 1: Build the Network and Configure Basic Device Settings

Part 2: Configure Switches with VLANs and Trunking

Part 3: Verify Trunking, VLANs, Routing, and Connectivity

Background / Scenario

Legacy inter-VLAN routing is seldom used in today's networks; however, it is helpful to configure and understand this type of routing before moving on to router-on-a-stick (trunk-based) inter-VLAN routing or

Lab – Configuring Per-Interface Inter-VLAN Routing

configuring Layer-3 switching. Also, you may encounter per-interface inter-VLAN routing in organizations with very small networks. One of the benefits of legacy inter-VLAN routing is ease of configuration.

In this lab, you will set up one router with two switches attached via the router Gigabit Ethernet interfaces. Two separate VLANs will be configured on the switches, and you will set up routing between the VLANs.

Note: This lab provides minimal assistance with the actual commands necessary to configure the router and switches. The required switch VLAN configuration commands are provided in Appendix A of this lab. Test your knowledge by trying to configure the devices without referring to the appendix.

Note: The routers used with CCNA hands-on labs are Cisco 1941 Integrated Services Routers (ISRs) with Cisco IOS, Release 15.2(4)M3 (universalk9 image). The switches used are Cisco Catalyst 2960s with Cisco IOS, Release 15.0(2) (lanbasek9 image). Other routers, switches and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and output produced might vary from what is shown in the labs. Refer to the Router Interface Summary Table at the end of this lab for the correct interface identifiers.

Note: Make sure that the routers and switches have been erased and have no startup configurations. If you are unsure, contact your instructor.

Required Resources

- 1 Router (Cisco 1941 with Cisco IOS Release 15.2(4)M3 universal image or comparable)
- 2 Switches (Cisco 2960 with Cisco IOS Release 15.0(2) lanbasek9 image or comparable)
- 2 PCs (Windows 7, Vista, or XP with terminal emulation program, such as Tera Term)
- Console cables to configure the Cisco IOS devices via the console ports
- Ethernet cables as shown in the topology

Part 1: Build the Network and Configure Basic Device Settings

In Part 1, you will set up the network topology and clear any configurations, if necessary.

Step 1: Cable the network as shown in the topology.

Step 2: Initialize and reload the router and switches.

Step 3: Configure basic settings for R1.

- a. Console into R1 and enter global configuration mode.
- b. Copy the following basic configuration and paste it to the running-configuration on R1.

```
no ip domain-lookup
hostname R1
service password-encryption
enable secret class
banner motd #
Unauthorized access is strictly prohibited. #
line con 0
password cisco
login
logging synchronous
line vty 0 4
password cisco
```

```
login
```

- c. Configure addressing on G0/0 and G0/1 and enable both interfaces.
- d. Copy the running configuration to the startup configuration.

Step 4: Configure basic settings on both switches.

- a. Console into the switch and enter global configuration mode.
- b. Copy the following basic configuration and paste it to running-configuration on the switch.

```
no ip domain-lookup
service password-encryption
enable secret class
banner motd #
Unauthorized access is strictly prohibited. #
Line con 0
password cisco
login
logging synchronous
line vty 0 15
password cisco
login
exit
```

- c. Configure the host name as shown in the topology.
- d. Copy the running configuration to the startup configuration.

Step 5: Configure basic settings on PC-A and PC-B.

Configure PC-A and PC-B with IP addresses and a default gateway address according to the Addressing Table.

Part 2: Configure Switches with VLANs and Trunking

In Part 2, you will configure the switches with VLANs and trunking.

Step 1: Configure VLANs on S1.

- a. On S1, create VLAN 10. Assign **Student** as the VLAN name.
- b. Create VLAN 20. Assign **Faculty-Admin** as the VLAN name.
- c. Configure F0/1 as a trunk port.
- d. Assign ports F0/5 and F0/6 to VLAN 10 and configure both F0/5 and F0/6 as access ports.
- e. Assign an IP address to VLAN 10 and enable it. Refer to the Addressing Table.
- f. Configure the default gateway according to the Addressing Table.

Step 2: Configure VLANs on S2.

- a. On S2, create VLAN 10. Assign **Student** as the VLAN name.
- b. Create VLAN 20. Assign **Faculty-Admin** as the VLAN name.
- c. Configure F0/1 as a trunk port.

Lab – Configuring Per-Interface Inter-VLAN Routing

- d. Assign ports F0/11 and F0/18 to VLAN 20 and configure both F0/11 and F0/18 as access ports.
- e. Assign an IP address to VLAN 10 and enable it. Refer to the Addressing Table.
- f. Configure the default gateway according to the Addressing Table.

Part 3: Verify Trunking, VLANs, Routing, and Connectivity

Step 1: Verify the R1 routing table.

- a. On R1, issue the **show ip route** command. What routes are listed on R1?

The 192.168.10.0/24 and 192.168.20.0/24 networks are listed on R1.

```
R1# show ip route
*Mar 25 15:05:00.003: %SYS-5-CONFIG_I: Configured from console by console
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
       + - replicated route, % - next hop override
Gateway of last resort is not set
  192.168.10.0/24 is variably subnetted, 2 subnets, 2 masks
C       192.168.10.0/24 is directly connected, GigabitEthernet0/1
L       192.168.10.1/32 is directly connected, GigabitEthernet0/1
  192.168.20.0/24 is variably subnetted, 2 subnets, 2 masks
C       192.168.20.0/24 is directly connected, GigabitEthernet0/0
L       192.168.20.1/32 is directly connected, GigabitEthernet0/0
```

- b. On both S1 and S2, issue the **show interface trunk** command. Is the F0/1 port on both switches set to trunk? Yes

```
S1# show interface trunk
```

```
Port      Mode          Encapsulation  Status        Native vlan
Fa0/1     on            802.1q         trunking      1
```

```
Port      Vlans allowed on trunk
Fa0/1     1-4094
```

```
Port      Vlans allowed and active in management domain
Fa0/1     1,10,20
```

```
Port      Vlans in spanning tree forwarding state and not pruned
Fa0/1     1,10,20
```

Lab – Configuring Per-Interface Inter-VLAN Routing

- c. Issue a **show vlan brief** command on both S1 and S2. Verify that VLANs 10 and 20 are active and that the proper ports on the switches are in the correct VLANs. Why is F0/1 not listed in any of the active VLANs?

It is a trunk port and is not assigned to a VLAN.

S1# **show vlan brief**

VLAN Name	Status	Ports
1 default	active	Fa0/2, Fa0/3, Fa0/4, Fa0/7 Fa0/8, Fa0/9, Fa0/10, Fa0/11 Fa0/12, Fa0/13, Fa0/14, Fa0/15 Fa0/16, Fa0/17, Fa0/18, Fa0/19 Fa0/20, Fa0/21, Fa0/22, Fa0/23 Fa0/24, Gi0/1, Gi0/2
10 Student	active	Fa0/5, Fa0/6
20 Faculty-Admin	active	
1002 fddi-default	act/unsup	
1003 token-ring-default	act/unsup	
1004 fddinet-default	act/unsup	
1005 trnet-default	act/unsup	

S2# **show vlan brief**

VLAN Name	Status	Ports
1 default	active	Fa0/2, Fa0/3, Fa0/4, Fa0/5 Fa0/6, Fa0/7, Fa0/8, Fa0/9 Fa0/10, Fa0/12, Fa0/13, Fa0/14 Fa0/15, Fa0/16, Fa0/17, Fa0/19 Fa0/20, Fa0/21, Fa0/22, Fa0/23 Fa0/24, Gi0/1, Gi0/2
10 Student	active	
20 Faculty-Admin	active	Fa0/11, Fa0/18
1002 fddi-default	act/unsup	
1003 token-ring-default	act/unsup	
1004 fddinet-default	act/unsup	
1005 trnet-default	act/unsup	

- d. Ping from PC-A in VLAN 10 to PC-B in VLAN 20. If Inter-VLAN routing is functioning correctly, the pings between the 192.168.10.0 network and the 192.168.20.0 should be successful.

Note: It may be necessary to disable the PC firewall to ping between PCs.

- e. Verify connectivity between devices. You should be able to ping between all devices. Troubleshoot if you are not successful.

Reflection

What is an advantage of using legacy inter-VLAN routing?

Answers may vary. Configuration of both the router and switches is relatively easy and straightforward. No subinterfaces are required on the router and trunking does NOT have to be configured between the router and switch.

Router Interface Summary Table

Router Interface Summary				
Router Model	Ethernet Interface #1	Ethernet Interface #2	Serial Interface #1	Serial Interface #2
1800	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
1900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
2801	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/1/0 (S0/1/0)	Serial 0/1/1 (S0/1/1)
2811	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
2900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)

Note: To find out how the router is configured, look at the interfaces to identify the type of router and how many interfaces the router has. There is no way to effectively list all the combinations of configurations for each router class. This table includes identifiers for the possible combinations of Ethernet and Serial interfaces in the device. The table does not include any other type of interface, even though a specific router may contain one. An example of this might be an ISDN BRI interface. The string in parenthesis is the legal abbreviation that can be used in Cisco IOS commands to represent the interface.

Appendix A: Configuration Commands

Switch S1

```
S1(config)# vlan 10
S1(config-vlan)# name Student
S1(config-vlan)# exit
S1(config)# vlan 20
S1(config-vlan)# name Faculty-Admin
S1(config-vlan)# exit
S1(config)# interface f0/1
S1(config-if)# switchport mode trunk
S1(config-if)# interface range f0/5 - 6
S1(config-if-range)# switchport mode access
S1(config-if-range)# switchport access vlan 10
S1(config-if-range)# interface vlan 10
S1(config-if)# ip address 192.168.10.11 255.255.255.0
S1(config-if)# no shut
```

Lab – Configuring Per-Interface Inter-VLAN Routing

```
S1(config-if)# exit
S1(config)# ip default-gateway 192.168.10.1
```

Switch S2

```
S2(config)# vlan 10
S2(config-vlan)# name Student
S2(config-vlan)# exit
S2(config)# vlan 20
S2(config-vlan)# name Faculty-Admin
S2(config-vlan)# exit
S2(config)# interface f0/1
S2(config-if)# switchport mode trunk
S2(config-if)# interface f0/11
S2(config-if)# switchport mode access
S2(config-if)# switchport access vlan 20
S2(config-if)# interface f0/18
S2(config-if)# switchport mode access
S2(config-if)# switchport access vlan 20
S2(config-if-range)# interface vlan 10
S2(config-if)# ip address 192.168.10.12 255.255.255.0
S2(config-if)# no shut
S2(config-if)# exit
S2(config)# ip default-gateway 192.168.10.1
```

Device Configs

Note: The VLANs configured do not display in the switch running configuration but are stored in the vlan.dat file.

Router R1

```
R1#show run
Building configuration...

Current configuration : 1640 bytes
!
version 15.2
service timestamps debug datetime msec
service timestamps log datetime msec
no service password-encryption
!
hostname R1
!
boot-start-marker
boot-end-marker
!
!
enable secret 4 06YFDUHH61wAE/kLkDq9BGho1QM5EnRtoyr8cHAUg.2
!
no aaa new-model
```

Lab – Configuring Per-Interface Inter-VLAN Routing

```
!  
!  
!  
!  
no ip domain lookup  
ip cef  
no ipv6 cef  
!  
multilink bundle-name authenticated  
!  
!  
!  
!  
redundancy  
!  
!  
!  
!  
!  
!  
!  
interface Embedded-Service-Engine0/0  
no ip address  
shutdown  
!  
interface GigabitEthernet0/0  
ip address 192.168.20.1 255.255.255.0  
duplex auto  
speed auto  
!  
interface GigabitEthernet0/1  
ip address 192.168.10.1 255.255.255.0  
duplex auto  
speed auto  
!  
interface Serial0/0/0  
no ip address  
shutdown  
clock rate 2000000  
!  
interface Serial0/0/1  
no ip address  
shutdown  
!  
ip forward-protocol nd  
!  
no ip http server  
no ip http secure-server  
!
```

Lab – Configuring Per-Interface Inter-VLAN Routing

```
!  
!  
!  
control-plane  
!  
!  
!  
line con 0  
  password cisco  
  login  
line aux 0  
line 2  
  no activation-character  
  no exec  
  transport preferred none  
  transport input all  
  transport output pad telnet rlogin lapb-ta mop udptn v120 ssh  
  stopbits 1  
line vty 0 4  
  password cisco  
  login  
  transport input all  
!  
scheduler allocate 20000 1000  
!  
end
```

Switch S1

```
S1# show vlan brief
```

VLAN	Name	Status	Ports
1	default	active	Fa0/2, Fa0/3, Fa0/4, Fa0/7 Fa0/8, Fa0/9, Fa0/10, Fa0/11 Fa0/12, Fa0/13, Fa0/14, Fa0/15 Fa0/16, Fa0/17, Fa0/18, Fa0/19 Fa0/20, Fa0/21, Fa0/22, Fa0/23 Fa0/24, Gi0/1, Gi0/2
10	Student	active	Fa0/5, Fa0/6
20	Faculty-Admin	active	
1002	fddi-default	act/unsup	
1003	token-ring-default	act/unsup	
1004	fddinet-default	act/unsup	
1005	trnet-default	act/unsup	

```
S1#show run
```

```
Building configuration...
```

```
Current configuration : 1644 bytes
```

Lab – Configuring Per-Interface Inter-VLAN Routing

```
!  
version 15.0  
no service pad  
service timestamps debug datetime msec  
service timestamps log datetime msec  
no service password-encryption  
!  
hostname S1  
!  
!  
enable secret 4 06YFDUHH61wAE/kLkDq9BGho1QM5EnRtoyr8cHAUg.2  
!  
no aaa new-model  
system mtu routing 1500  
!  
!  
no ip domain-lookup  
!  
interface FastEthernet0/1  
  switchport mode trunk  
!  
interface FastEthernet0/2  
!  
interface FastEthernet0/3  
!  
interface FastEthernet0/4  
!  
interface FastEthernet0/5  
  switchport access vlan 10  
  switchport mode access  
!  
interface FastEthernet0/6  
  switchport access vlan 10  
  switchport mode access  
!  
interface FastEthernet0/7  
!  
interface FastEthernet0/8  
!  
interface FastEthernet0/9  
!  
interface FastEthernet0/10  
!  
interface FastEthernet0/11  
!  
interface FastEthernet0/12  
!  
interface FastEthernet0/13  
!
```

Lab – Configuring Per-Interface Inter-VLAN Routing

```
interface FastEthernet0/14
!
interface FastEthernet0/15
!
interface FastEthernet0/16
!
interface FastEthernet0/17
!
interface FastEthernet0/18
!
interface FastEthernet0/19
!
interface FastEthernet0/20
!
interface FastEthernet0/21
!
interface FastEthernet0/22
!
interface FastEthernet0/23
!
interface FastEthernet0/24
!
interface GigabitEthernet0/1
!
interface GigabitEthernet0/2
!
interface Vlan1
  no ip address
  shutdown
!
interface Vlan10
  ip address 192.168.10.11 255.255.255.0
!
ip default-gateway 192.168.10.1
ip http server
ip http secure-server
!
!
line con 0
  password cisco
  login
line vty 0 4
  password cisco
  login
line vty 5 15
  password cisco
  login
!
end
```

Lab – Configuring Per-Interface Inter-VLAN Routing

Switch S2

```
S2# show vlan brief
```

VLAN Name	Status	Ports
1 default	active	Fa0/2, Fa0/3, Fa0/4, Fa0/5 Fa0/6, Fa0/7, Fa0/8, Fa0/9 Fa0/10, Fa0/12, Fa0/13, Fa0/14 Fa0/15, Fa0/16, Fa0/17, Fa0/19 Fa0/20, Fa0/21, Fa0/22, Fa0/23 Fa0/24, Gi0/1, Gi0/2
10 Student	active	
20 Faculty-Admin	active	Fa0/11, Fa0/18
1002 fddi-default	act/unsup	
1003 token-ring-default	act/unsup	
1004 fddinet-default	act/unsup	
1005 trnet-default	act/unsup	

```
S2#sh run
```

```
Building configuration...
```

```
Current configuration : 1644 bytes
```

```
!  
version 15.0  
no service pad  
service timestamps debug datetime msec  
service timestamps log datetime msec  
no service password-encryption  
!  
hostname S2  
!  
enable secret 4 06YFDUHH61wAE/kLkDq9BGho1QM5EnRtoyr8cHAUg.2  
!  
no aaa new-model  
system mtu routing 1500  
!  
!  
no ip domain-lookup  
!  
interface FastEthernet0/1  
switchport mode trunk  
!  
<Output Omitted>  
interface FastEthernet0/10  
!  
interface FastEthernet0/11  
switchport access vlan 20  
switchport mode access  
!
```

Lab – Configuring Per-Interface Inter-VLAN Routing

```
interface FastEthernet0/12
!
interface FastEthernet0/13
!
interface FastEthernet0/14
!
interface FastEthernet0/15
!
interface FastEthernet0/16
!
interface FastEthernet0/17
!
interface FastEthernet0/18
switchport access vlan 20
switchport mode access
!
!interface FastEthernet0/19
!
interface FastEthernet0/20
!
interface FastEthernet0/21
!
interface FastEthernet0/22
!
interface FastEthernet0/23
!
interface FastEthernet0/24
!
interface GigabitEthernet0/1
!
interface GigabitEthernet0/2
!
interface Vlan1
no ip address
shutdown
!
interface Vlan10
ip address 192.168.10.12 255.255.255.0
!
ip default-gateway 192.168.10.1
ip http server
ip http secure-server
!
line con 0
line vty 0 4
password cisco
login
line vty 5 15
password cisco
```

Lab – Configuring Per-Interface Inter-VLAN Routing

```
login  
end
```