


## Packet Tracer – Configuring Rapid PVST+ (Instructor Version)

**Instructor Note:** Red font color or Gray highlights indicate text that appears in the instructor copy only.

### Topology



### Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
S1	VLAN 99	172.17.99.11	255.255.255.0	N/A
S2	VLAN 99	172.17.99.12	255.255.255.0	N/A
S3	VLAN 99	172.17.99.13	255.255.255.0	N/A
PC1	NIC	172.17.10.21	255.255.255.0	172.17.10.254
PC2	NIC	172.17.20.22	255.255.255.0	172.17.20.254
PC3	NIC	172.17.30.23	255.255.255.0	172.17.30.254

### Switch Port Assignment Specifications

Ports	Assignments	Network
S2 F0/6	VLAN 30	172.17.30.0/24
S2 F0/18	VLAN 20	172.17.20.0/24
S2 F0/11	VLAN 10	172.17.10.0/24

### Objectives

#### Part 1: Configure VLANs

### Part 2: Configure Rapid Spanning Tree PVST+ Load balancing

### Part 3: Configure PortFast and BPDU Guard

## Background

In this activity, you will configure VLANs and trunks, Rapid Spanning Tree PVST+, primary and secondary root bridges, and examine the configuration results. You will also optimize the network by configuring PortFast, and BPDU Guard on edge ports.

## Part 1: Configure VLANs

### Step 1: Enable the user ports on S2 in access mode.

Refer to the topology diagram to determine which switch ports on **S2** are activated for end-user device access. These three ports will be configured for access mode and enabled with the **no shutdown** command.

```
S2(config)# interface range f0/6,f0/11,f0/18
S2(config-if-range)# switchport mode access
S2(config-fi-range)# no shutdown
```

### Step 2: Create VLANs.

Using the appropriate command, create VLANs 10, 20, 30, 40, 50, 60, 70, 80, and 99 on all of the switches.

```
S1(config)# vlan 10
S1(config-vlan)# vlan 20
S1(config-vlan)# vlan 30
S1(config-vlan)# vlan 40
S1(config-vlan)# vlan 50
S1(config-vlan)# vlan 60
S1(config-vlan)# vlan 70
S1(config-vlan)# vlan 80
S1(config-vlan)# vlan 99
```

```
S2(config)# vlan 10
S2(config-vlan)# vlan 20
S2(config-vlan)# vlan 30
S2(config-vlan)# vlan 40
S2(config-vlan)# vlan 50
S2(config-vlan)# vlan 60
S2(config-vlan)# vlan 70
S2(config-vlan)# vlan 80
S2(config-vlan)# vlan 99
```

```
S3(config)# vlan 10
S3(config-vlan)# vlan 20
S3(config-vlan)# vlan 30
S3(config-vlan)# vlan 40
S3(config-vlan)# vlan 50
S3(config-vlan)# vlan 60
```

```
S3(config-vlan)# vlan 70
S3(config-vlan)# vlan 80
S3(config-vlan)# vlan 99
```

### Step 3: Assign VLANs to switch ports.

Port assignments are listed in the table at the beginning of the activity. Save your configurations after assigning switch ports to the VLANs.

```
S2(config)# interface f0/6
S2(config-if)# switchport access vlan 30
S2(config-if)# interface f0/11
S2(config-if)# switchport access vlan 10
S2(config-if)# interface f0/18
S2(config-if)# switchport access vlan 20
```

### Step 4: Verify the VLANs.

Use the **show vlan brief** command on all switches to verify that all VLANs are registered in the VLAN table.

### Step 5: Assign the trunks to native VLAN 99.

Use the appropriate command to configure ports F0/1 to F0/4 on each switch as trunk ports and assign these trunk ports to native VLAN 99.

```
S1(config)# interface range f0/1-4
S1(config-if-range)# switchport mode trunk
S1(config-if-range)# switchport trunk native vlan 99

S2(config)# interface range f0/1-4
S2(config-if-range)# switchport mode trunk
S2(config-if-range)# switchport trunk native vlan 99

S3(config)# interface range f0/1-4
S3(config-if-range)# switchport mode trunk
S3(config-if-range)# switchport trunk native vlan 99
```

### Step 6: Configure the management interface on all three switches with an address.

```
S1(config)# interface vlan99
S1(config-if)# ip address 172.17.99.11 255.255.255.0

S2(config)# interface vlan99
S2(config-if)# ip address 172.17.99.12 255.255.255.0

S3(config)# interface vlan99
S3(config-if)# ip address 172.17.99.13 255.255.255.0
```

Verify that the switches are correctly configured by pinging between them.

## Part 2: Configure Rapid Spanning Tree PVST+ Load Balancing

The Rapid Spanning Tree Protocol (RSTP; IEEE 802.1w) can be seen as an evolution of the 802.1D standard more so than a revolution. The 802.1D terminology remains primarily the same. Most parameters have been left unchanged so users familiar with 802.1D can rapidly configure the new protocol comfortably. In most cases, RSTP performs better than proprietary extensions of Cisco without any additional configuration. 802.1w can also revert back to 802.1D in order to interoperate with legacy bridges on a per-port basis.

### Step 1: Configure STP mode.

Use the **spanning-tree mode** command to configure the switches to use rapid PVST as the STP mode.

```
S1(config)# spanning-tree mode rapid-pvst
```

```
S2(config)# spanning-tree mode rapid-pvst
```

```
S3(config)# spanning-tree mode rapid-pvst
```

### Step 2: Configure Rapid Spanning Tree PVST+ load balancing.

Configure **S1** to be the primary root for VLANs 1, 10, 30, 50, and 70. Configure **S3** to be the primary root for VLANs 20, 40, 60, 80, and 99. Configure **S2** to be the secondary root for all of the VLANs.

```
S1(config)# spanning-tree vlan 1,10,30,50,70 root primary
```

```
S2(config)# spanning-tree vlan 1,10,20,30,40,50,60,70,80,99 root secondary
```

```
S3(config)# spanning-tree vlan 20,40,60,80,99 root primary
```

Verify your configurations by using the **show spanning-tree** command.

## Part 3: Configure PortFast and BPDU Guard

### Step 1: Configuring PortFast on S2.

PortFast causes a port to enter the forwarding state almost immediately by dramatically decreasing the time of the listening and learning states. PortFast minimizes the time it takes for the server or workstation to come online. Configure PortFast on **S2** interfaces that are connected to PCs.

```
S2(config)# interface range f0/6 , f0/11 , f0/18
```

```
S2(config-if-range)# spanning-tree portfast
```

### Step 2: Configuring BPDU Guard on S2.

The STP PortFast BPDU Guard enhancement allows network designers to enforce the STP domain borders and keep the active topology predictable. The devices behind the ports that have STP PortFast enabled are not able to influence the STP topology. At the reception of BPDUs, the BPDU Guard operation disables the port that has PortFast configured. The BPDU Guard transitions the port into err-disable state, and a message appears on the console. Configure BPDU Guard on **S2** interfaces that are connected to PCs.

```
S2(config)# interface range f0/6 , f0/11 , f0/18
```

```
S2(config-if-range)# spanning-tree bpduguard enable
```

### Step 3: Verify your configuration.

Use the **show run** command to verify your configuration.